


GRANADA UNIVERSITY (UGR)



**THEORETICAL PHYSICS AND THE COSMOS
DEPARTMENT**

**ANDALUSIAN INSTITUTE OF GEOPHYSICS AND
PREVENTION OF SEISMIC DISASTERS**

“Seismic Signals Integration System”

(Sistema de Integración para Registros Sísmicos)

USER MANUAL: VERSION 1.0

Author:

Ligdamis A. Gutiérrez E. PhD.

Masaya Volcano, Nicaragua

Photo by: Ligdamis A. Gutiérrez E.

Granada, Spain 2021 - 2023

General Index

1.- Introduction	3
2.- Initial Screen of the System	4
2.1.- Elements of the Initial Screen	6
3.- Analysis Interface	7
3.1.- Analysis Screen Elements	7
3.1.1.- Selection Block	7
3.2.- Selection block Elements	8
3.2.1.- Load Record Button	8
3.2.2.- Clean Inputs Button	9
3.2.3.- Filter Type Selection	10
3.2.4.- Input Selection	10
3.2.5.- Lowpass Filter	11
3.2.6.- Highpass Filter	12
3.2.7.- Bandpass Filter	13
3.2.8.- Bandstop Filter	15
4.- Register path block	16
5.- Command Block	17
5.1.- Error Validation in Records or Entries	18
6.- Filter and Analysis Sections Results	18
6.1.- Example of Lowpass filter selection results and integral calculation	18
6.2.- Example of Bandpass filter selection results and integral calculation	19
7.- Resulting graphs	20
7.1.- Filter and Zoom records graphs	20
7.1.1.- Record calculating in SAC format example	21
7.1.2.- Example of Calculation of a VLP event, record with MSEED format	23
8.- Graph Toolbar (Matplotlib)	26
8.1.- Save the Graphs	26
8.2.- Editing the Axes and Images of the Graphs	28
Conclusion	31
Acknowledgments	31
Appendix A	32
A1.- Installation of Python and Additional Libraries	32
A1.1. Installation Package Contents	32
A1.2.- Installing Python on Windows	32
A1.3.- Additional libraries installing	33
A1.4 Automatic installation of libraries in Windows and Linux from the PIP	36
Appendix B	37
Python libraries install, for the accurate system functioning	37

The **Seismic Signals Integration System** module is a user-friendly interface that allows for easy and efficient management of seismic-volcanic signal integration. Determining the integral of a signal can be extremely useful, especially in the case of **Very Long Period (VLP)** events. These types of events are known as very low-frequency events, typically ranging from 0.01 to 0.5 Hz (*periods between 2 and 100 seconds*). They are associated with very large wavelengths, extending from tens to hundreds of kilometers, and are related to resonant oscillations within the shallow magma conduit systems of volcanic structures. They are often accompanied by explosions. Easy access to signal integral calculation, combined with the ability to apply filtering techniques, provides a reliable automated tool to assist operators in identifying and verifying the mass displacement phenomenon in VLP events, which may be due to the movement of fluids or gases.

The application, through its incorporated libraries, allows for the reading of various seismic formats such as SAC, MSEED, GSE2, EVT, WAV, among others. Various filtering techniques can then be applied, automatically providing added value to the operator's expertise by enabling faster and more accurate identification of seismic waves compared to manual analysis in a continuous record.

The first version of this system consists of a single interface that includes tools for signal filtering and the process of cutting a specific event from an original seismic trace, whether measured in minutes, hours, or days. The main interface includes an English version of the system. However, the documentation, including this document, is available in Spanish. In the appendices, you will find information about the folder structure and its contents. The system also provides the ability to store the conversion of events at multiple frequencies according to the observer's criteria, which can be used in seismic institutes and observatories. Additionally, if desired, the event or record being converted can be graphically displayed, and the graphical results can be saved in various formats such as PNG, JPG, EPS, PS, PDF, RAF, TIF, among others.

The module and the entire system have been developed in Python, version 3.8.6. (The set of libraries is compatible with version 3.10.10). Additionally, a series of open-access libraries are included, which, in conjunction with Python, enable the use of graphical and analytical tools, providing ease of use and enhancing computational power for the user. Some of the main elements and libraries used are listed below:

- **Matplotlib**: Used for creating static, animated, and interactive visualizations in Python. (<https://matplotlib.org/stable/users/index.html>).
- **NumPy**: A library for numerical operations in Python. (<https://numpy.org/doc/stable/user/quickstart.html>).
- **PyQt5**: A tool that links with the graphical library Qt5 in C++ (<https://pyqt.org/project/pyqt5/>).
- **Obspy**: A Python toolbox for seismology. (<https://docs.obspy.org/>).
- **Tkinter**: Graphical User Interface (GUI) (<https://docs.python.org/3/library/tkinter.html>)

Another key feature of the system is its definition as a cross-platform application, meaning it can operate on various platforms or operating systems, such as Windows (7, 8, 10, 11) in both 32-bit and 64-bit versions. It also supports Linux systems, such as Ubuntu and other similar systems (Debian, Red Hat, Fedora, SUSE, etc.), macOS, and Android for tablets and mobile devices (with Python appropriately adapted for these devices).

NOTE: In the appendices of this document (*as well as in the Readme.txt and Initial_requirements.txt files*), you can find general information on installation for Windows and Linux systems, as well as guidelines for installing the main programs and additional libraries required by Python to properly execute the developed programs in its environment.

2.- Initial Screen of the System

[Back to Index](#)

In the appendices of this document and in the “**README.txt**” file included in the “**Documents**” folder, you will find instructions for installing the system on Windows (*the process on Linux systems is similar*). Essentially, you need to perform two actions:

- Copy the “Set_tools_System_1_1” folder to “My Documents” on Windows.
- Copy the “Set_tools_System_1_1.bat” file to the Windows desktop.

Additionally, there are instructions for installing the necessary Python libraries on the system. Once “Set_tools_System_1_1.bat” has been copied to the desktop, you need to right-click on it and select “Run as administrator.”



Fig. 1 Popup Window when Right-Clicking on the “Set_tools_System_1_1.bat” File

In the window that opens, click the “Yes” button when prompted with “*Do you want to allow this app to make changes to your computer?*” This is a warning message. However, the application does not make any changes, so you should trust its execution.

Upon clicking “Yes,” the following command window opens, welcoming you to the system.




Fig. 2 Welcome Screen and Instructions for Loading the System.

After reading the information in the window, you simply need to press any key to access the system's initial screen. The folder should already be copied to “**My Documents**,” and the “**Set_tools_System_1_1.bat**” file contains all the loading instructions.

The system's initial screen is “**Menu.py**”. It appears when any key is pressed on the Welcome screen. Additionally, the Python command window or console is displayed, similar to the following:





Fig. 3 Python Console (CMD) Window (*Should be minimized*)

To avoid obstructing the view, you can and should "minimize" this screen. Do **not** close it, as this would also close the system's startup window. Once you have finished working with the system, this window will close automatically. The initial presentation screen of the system (the module menu) “**Menu.py**” is as follows:




NOTE: When pressing or clicking on a module button, the startup window will close and the module window will open (*this may take a little time depending on the PC's memory. It is recommended to have at least 8 GB of memory in the system, with 16 GB being ideal*).

Fig. 4 Main Menu Screen. The module to be worked on is highlighted. Module 4 (*Converting Seismic Records to Wav*).


2.1.- Elements of the Initial Screen.

As observed in the previous figure, the initial or presentation screen is a simple window composed of:

- a) A top toolbar with basic information about the module.
 - b) On the left side, there are 10 execution buttons or command buttons for each module of the system.
 - c) At the bottom, there is a command button that allows for exiting the system.
 - d) Additionally, it features a background image representing a volcano (Masaya in Nicaragua), and three images with the logos of the University of Granada, the Andalusian Institute of Geophysics, and the Department of Theoretical and Cosmic Physics.
- a) At the top, the icon of the University is visible, along with the module title and a reference to the University of Granada (UGR).



- b) On the left side, there are 10 execution buttons or command buttons for each module of the system. When the mouse pointer is placed over each button, it is highlighted in white to indicate that it is being selected. Clicking on a button closes the startup menu window and opens the window for the indicated module (this may take a little time depending on the PC's memory).



- c) At the bottom, there is a command button: **Exit**. When the mouse pointer is placed over each button, a text appears indicating the action of that button (Exit System, Start System).



If you click the "Exit" button, a window will appear asking the user if they are sure they want to leave the system.




Fig. 5 Text Box Indicating Whether You Want to Exit the System.

If you click "**OK**," the screen will close and the system will exit. If you click "Cancel," you will remain on the initial screen.

3.- Main analysis interface.

The "analysis screen" is the main interface of the module, where activities for record reading, filtering, and spectral analysis of seismic records are carried out. This screen is composed of the following parts:





Fig. 6 Elements of the Analysis Screen Module.

- 1) **Title Area:** (Module name and the University)
- 2) **Load and Clean Block:** a) Command buttons: Load Record and Clean buttons, parameters b) Filter Types.
- 3) **Route Block:** Physical location path of the record to be analyzed.
- 4) **Command Block:** a) Command buttons (Integral Plot/Graph, Go Back, and Exit).

The screen consists of various elements for user interaction. At the top, it displays the program name, icon, and the university name as the title (1).



The elements that make up the main screen are detailed below.

3.1.- Analysis screen elements.

Added to number (1), the 3 elements of the initial fusion interface screen have been distributed into three main blocks, numbered (2-4) in red circles.

3.1.1.- Selection Block. (2)



Fig. 7 Selection Elements Block. In the green circles: a) **Command Buttons:** Load Record, Clean b) **Filter Types** c) **Data Input.**

3.2.- Elements of the selection block.

This block is configured (green circles in the previous figure) with, first, the section that groups the action buttons for loading the record and data cleaning: (**Command Buttons: *Load Record* and *Clean***).




Fig. 8 **Record and Data Cleaning Buttons**: Action messages are displayed on each button.

As can be seen, the **Load Record** button performs the search and loading of seismic records in various formats. The **Clean** button clears the input elements, closes the existing graphs, and resets the analysis screen to its initial state, preparing it for a new search and analysis of seismic events.

3.2.1.- Command button “Load Record”: Ensure that the files and directory are selected.



The action of the **Load Record** button allows users to click and open an explorer window (by default, it points to the root directory “C” of the PC), presenting options for various types of formats to search for and enabling the search within the computer's directory. This is shown in the following screen.




Fig. 9 Record Selection Screen.

In this screen (the language is determined by the operating system), records are selected according to the desired format (red box) such as SAC, MSEED, GSE2, EVT, etc. This is made possible through the “**Obspy**” library for reading seismic formats.

Once selected, clicking the “**Open**” button will load the record onto the analysis screen. Conversely, clicking the “**Cancel**” button will return the action to the analysis screen. The process of selecting a record is shown in the following screen.




Fig. 10 Example screen of selecting a “SAC” format record.

In the screen, at the bottom right, indicated by the red circle and highlighted by the arrow, is the list of the most commonly supported and/or used seismic formats in observatories and institutes worldwide (*SAC*, *MSEED*, *GSE2*, *WAV*, *EVT*).

When selecting a specific type, the records are presented according to that format. For example, the 'SAC' files. By clicking on the desired record, as shown, it populates the “**Name**” box. At this point, you click the button that was shown in the previous screen, “**Open**”, which loads the address or “**Path**” of the physical location of the record in the system.




Fig. 11 File path box, which shows the location of the record.

This is an important aspect, as it determines whether the physical file containing the record can be located on the computer for analysis. If the file is invalid, not found, or if the parameters are incorrect, a validation window will appear to indicate the issue (Cfr. Fig. 28, Pág. 18).

3.2.2.- Clean Inputs Button.

Clicking this button clears all entries on the screen. It will clean the data entry text boxes and the path or folder where the record to be downloaded will be stored, and it will delete all active entries with data at that moment. It restores the initial values of the main interface (see Fig. 6).

When you place the mouse pointer over it, a message appears indicating its function. Clicking the button opens a window asking the user if they are sure they want to delete the data entries. If confirmed, it clears all entries and returns the interface to its initial state. Otherwise, the current entries remain in the interface.



3.2.3.- Filter Type Selection.




Fig. 12 Filter Type Selection via List.

The previous figure shows a dropdown list with various types of filters available for analyzing records. As observed, it includes filter types such as *Lowpass*, *Highpass*, *Bandpass*, and *Bandstop*. Selecting each of these items will activate one or more of the checkboxes in the continuous section, which correspond to the data inputs required for performing the calculations. At the initial value "*Please Select*", the inputs return to their default values.

3.2.4.- Input Selection.



Fig. 13 Selection of the input to calculate and the trace number of the record (default = 0).

The inputs correspond to the selected filter type specified by the operator (default filter order = 4). Initially, all checkboxes are deactivated and will only be activated based on the chosen filter type. The trace number is set to default = 0. If there are multiple traces, such as in MSEED or SEISAN records with three components or various values, the desired trace number, starting from zero, should be entered in this text box. The inputs are validated to accept only numbers, including decimals and negative values. The activation/deactivation responds to the following:

I) The boxes in the area (a): {Frequency (Hz), Filter Order, Frec. Min (Hz), Frec. Max (Hz)}

1.- *Lowpass* and *Highpass* Filter.

Enable: {Frequency (Hz), Filter Order, Trace number st (n)}.

Disable: {Frec. Min (Hz), Frec. Max (Hz)}.

2.- *Bandpass*) and *Bandstop* Filter.

Enable: {Frec. Min (Hz), Frec. Max (Hz), Filter Order, Trace number st (n)}.

Disable: {Frequency (Hz)}.

II) The box in the area (b): {Trace number st(n)}. Enabled with all types of filters.

Regarding each type of filter, the checkboxes that are activated with the input parameters are as follows:

3.2.5.- *Lowpass*¹ Filter Type.


Fig. 14 Example of *Lowpass* Filter Selection. In the red circle: "Frequency" input, in the yellow circle: "Filter Order", in the green circle: "Trace Number".

When selecting this type of filter, the following checkboxes are activated:

- Filter Frequency (Hz):** Floating-point value. Here, you should enter a valid frequency value for the filter calculation (Red circle). In the example, the frequency value entered is "0.86 Hz".
- Filter Order:** Integer value. This field should be set to a valid filter order for the calculation. Typically, this is order 2 or 4 (by default, it is set to 4 for all analyses) (Yellow circle).
- Trace Number st (0):** Integer value. Determines the trace number to be analyzed. By default, and in formats like "SAC," this value is "0." For multiple traces, such as in "MSEED" formats, the user specifies which trace number they wish to analyze.

The "Frec. Min (Hz)/Minimum Frequency" and "Frec. Max (Hz)/Maximum Frequency" checkboxes remain inactive.

Once the actions for loading the record are completed and the filter type is selected, click on the "Plot Integral" button. If an attempt is made to graph (by clicking the Plot Integral button) with invalid input or a nonexistent record or out-of-range format in any of the fields, a validation dialog box will appear, indicating that the action must be performed.



These dialog boxes also ensure that the program can continue running without severe interruptions to the system due to lack of data. The validations for incorrect entries are as follows:

¹ The Lowpass filter blocks high-frequency signals and allows low-frequency signals (frequencies below the cutoff frequency) to pass through.




Fig. 15 Validation of entries for the *Lowpass* filter.

Once the inputs are corrected by entering a valid value or one within the permitted range, the program can continue and display the corresponding graph.

3.2.6.- *Highpass*² Filter type




Fig. Example of *Highpass* Filter Selection. In the red circle: "Frequency" input, in the yellow circle: "Filter Order", in the green circle: "Trace Number".


Similar to the previous filter, the following checkboxes are activated:

- Filter Frequency (Hz):** Floating-point value. Here, you should enter a valid frequency value for the filter calculation (Red circle). In the example, the frequency value entered is "15 Hz."
- Filter Order:** Integer value. This field should be set to a valid filter order for the calculation. Typically, this is order 2 or 4 (by default, it is set to 4 for all analyses) (Yellow circle).
- Trace Number st (0):** Integer value. Determines the trace number to be analyzed. By default, and in formats like "SAC," this value is "0." For multiple traces, such as in "MSEED" formats, the user specifies which trace number they wish to analyze.

The "Frec. Min (Hz)/Minimum Frequency" and "Frec. Max (Hz)/Maximum Frequency" checkboxes remain inactive.

² The **Highpass Filter** blocks low-frequency signals and allows high-frequency signals (*frequencies higher than the cutoff frequency*) to pass through.

Once the actions for loading the record are completed and the filter type is selected, click on the "Plot Integral" button. If an attempt is made to graph (by clicking the [Plot Integral](#) button) with invalid input or a nonexistent record or out-of-range format in any of the fields, a validation dialog box will appear, indicating that the action must be performed.



These dialog boxes also ensure that the program can continue running without severe interruptions to the system due to lack of data. The validations for incorrect entries are as follows:




Fig. 17 Validation of entries for the [Highpass](#) filter.

Once the inputs are corrected by entering a valid value or one within the permitted range, the program can continue and display the corresponding graph.

3.2.7.- [Bandpass](#)³ Filter Type.

Fig. 21 [Bandpass](#) Filter Selection Example. In the red circle, the entries "Minimum Frequency (Hz) and Maximum Frequency (Hz)"; yellow circle -> "Filter Order"; green circle -> Trace No.


³ The Bandpass filter allows spectral content to pass only within a range around the central frequency. This range is defined by a minimum frequency and a maximum frequency. It removes noise associated with both low and high frequencies that are outside this specified range.

Unlike the previous two filters, the following checkboxes are activated:

- a) **Minimum Filter Frequency (Hz):** Floating-point value. Enter a valid minimum frequency to define the start of the central window (Red circle). In the example, the value is "3 Hz."
- b) **Maximum Filter Frequency (Hz):** Floating-point value. Enter a valid maximum frequency to define the end of the central window (Red circle). In the example, the value is "12 Hz."
- c) **Filter Order:** Integer value. In this box, a valid value must be provided for the filter order to be used in the calculation, generally an order of 2 or 4 (by default, a value of 4 is set for all analyses) (yellow circle).
- d) **Trace number st (0):** Integer value. Determines the trace number to be analyzed. By default, and in formats like "SAC," this value is set to "0." For formats containing multiple traces, such as "MSEED" or "SEISAN," the user selects the trace number to analyze.

The "Frequency (Hz)/Filter Frequency" checkbox remains inactive.

Once the actions for loading the record are completed and the filter type is selected, click on the "Plot Integral" button. If you wish to plot, click the "Plot Integral" button. If there is an invalid entry, a nonexistent record, or an out-of-range format in any of the fields, a validation will appear, displaying a dialog box indicating that the action needs to be performed.



These dialog boxes also allow the program to continue running without severe system interruption due to missing data. The incorrect input validations are as follows:




Fig. 22 Validation of entries for the *Bandpass* filter.

3.2.8.- *Bandstop*⁴ Filter Type


Fig. 23 20 Example of *Bandstop* Filter Selection Type. In the red circle are the inputs “Minimum Frequency (Hz) and Maximum Frequency (Hz),” yellow circle -> “Filter Order” green circle -> Trace Number.

Similar to the Bandpass filter, the following checkboxes are activated for the Bandstop filter:

- Minimum Filter Frequency (Hz):** Floating-point value. Enter a valid minimum frequency to define the start of the central window (Red circle). In the example, the value is “1 Hz.”
- Maximum Filter Frequency (Hz):** Floating-point value. Enter a valid maximum frequency to define the end of the central window (Red circle). In the example, the value is “8 Hz.”
- Filter Order:** Integer value. In this box, a valid value must be provided for the filter order to be used in the calculation, generally an order of 2 or 4 (by default, a value of 4 is set for all analyses) (yellow circle).
- Trace number st (0):** Integer value. Determines the trace number to be analyzed. By default, and in formats like "SAC," this value is set to "0." For formats containing multiple traces, such as "MSEED" or "SEISAN," the user selects the trace number to analyze.

The "Frequency (Hz)/Filter Frequency" checkbox remains inactive.

Once the actions for loading the record are completed and the filter type is selected, click on the "Plot Integral" button. If you wish to plot, click the "Plot Integral" button. If there is an invalid entry, a nonexistent record, or an out-of-range format in any of the fields, a validation will appear, displaying a dialog box indicating that the action needs to be performed.



These dialog boxes also allow the program to continue running without severe system interruption due to missing data. The incorrect input validations are as follows:

⁴ The Bandstop filter blocks signals with frequencies between the upper and lower cutoff frequencies. In other words, it removes or attenuates a specific band of frequencies.




Fig. 24 Validation of entries for the *Bandstop* filter.

4.- Records and directory path Block.

3




Fig. 25 Physical path block of the file to load.

File Path Display Area (*Register path to load*): In this area, the path (*Disk/folder/file*), or “path” of the physical file (where it is stored on the computer), is displayed so it can be accessed by the system to perform the required calculations.

An example of the output after performing the calculations is shown in the following image.




Fig. 26 Example of the physical path of the file to load.

The “*Path*” (on the computer) of the record's location is displayed.

5.- Commands Block.

4




Fig. 27 Commands block

This last block consists of the following elements:


- a) **"Go Back" Button:** Allows returning to the initial system presentation screen. Hovering the mouse pointer over it displays a message indicating its function.




- b) **"Plot Integral" Button:** Once the filter types and the signal integral are selected, the calculations are performed, and the corresponding graphs are displayed. When the mouse pointer hovers over the button, a message appears indicating its function.



- c) **"Exit" button:** Allows for a complete exit from the system (*after displaying a prompt asking if you want to leave the system*). Hovering the mouse pointer over the button displays a message indicating its function.



In the same way as on the home screen, if the **"Exit" button** is clicked, a window will appear asking the user if they are sure they want to leave the system.



Clicking **"OK"** closes the screen and completes the system exit. **"Cancel"** returns to the analysis screen.

5.1.- Error validation in records or entries.

Clicking the “*Plot Integral*” will trigger an error validation if an invalid entry, non-existent record, or out-of-range format occurs. A dialog box will appear with an alert message indicating the issue. This allows the user to modify the entries or select a valid record without causing the system to crash or halt. The screen displayed is as follows:




Fig. 28 Validation of invalid entries, formats, or incorrect records.

According to the message in the previous figure, an error has occurred because the format is not recognized, or the record does not exist. Additionally, the parameters or entries might be out of the allowed range according to the signal being analyzed. By pressing the “*OK button*”, you return to the system to select a valid file or correct the erroneous entries. This way, the program continues to run without issues.

6.- Results of Filter and Analysis Sections.

A continuación, se procederá a presentar ejemplos de resultados finales del proceso de filtrado y cálculo de la integral.

6.1.- Example of Lowpass filtering selection results and integral calculation.

According to the entire process described above, the procedure for calculating the integral with a low-pass filter on the records is very simple and consists of the following steps:

- a) Open or select a specific record (the file path of the record is displayed as “*Register path to load.*” By default, the initial path is in the root directory “C” of the PC, whether on Windows or Linux systems).
- b) Select the low-pass filter (*Lowpass*).
- c) Enter the filter parameters.
- d) Click the “*Plot Integral*” button to graph the record.

All of this will produce:

The output of this analysis will consist of four graphs: the original signal, the filtered signal, the integral of the signal, and a combined view of all three (original, filtered, and integral). Each of these graphs allows for zooming in and can be saved in various formats.

The interface with the output elements is shown in the following figure.




Fig. Selection of parameters for the calculation of the integral of a **SAC** record, using a **Lowpass** filter.

In the figure, under “*Register Path to load*”, the full path where the record to be analyzed is stored is displayed. In the “*Filter Type*” list, the **Lowpass** filter has been selected. In the input field, a frequency of 0.86 Hz has been set, with a filter order = 4. The record contains only one trace, the default trace = “0”.

6.2.- Example of Bandpass filter selection results and integral calculation.

De acuerdo a todo el proceso anteriormente descrito, realizar el cálculo de la integral con filtro paso-banda de los registros es muy sencillo, consta de los siguientes pasos:

- Open or select a specific record (the file path of the record is displayed as "Seismic record path to upload." By default, the initial path is in the root directory "C" of the PC, whether on Windows or Linux systems).
- Select the band-pass filter (Bandpass).
- Enter the filter parameters.
- Click the "Plot Integral" button to graph the record.

All of this will present:

The output of this analysis will consist of four graphs: the original signal, the filtered signal, the integral of the signal, and a composite graph containing all three (original, filtered, and integral). Each of these graphs can be zoomed in on and saved in various formats.

The interface with the output elements is shown on the following page.




Fig. 30 Selection of parameters for the calculation of the integral of a **SAC** record, using a **Bandpass** filter.

In the figure, under "**File Path**", the full path where the record to be analyzed is stored is displayed. In the "Filter Type" list, the **Bandpass** filter has been selected. In the input field, a minimum frequency of 3 Hz and a maximum frequency =12 Hz have been set. The default filter order has been left at 4. The record contains only one trace, the default trace = "0".

The graphical results can be seen in the following sections.

7.- Resulting graphs.

Next, we will present an example of graphical results from the filtering process and the calculation of the signal integral.

7.1.- Filter Graphs and Zoom of Records.

As examples, the graphical results of the original record, the filtered record, and the integral of the signal for SAC and MSEED format records (VLP event) are presented.

Similarly, a zoom (using the Zoom tool [Magnifying Glass]) on the resulting graphs is shown (cf. *Matplotlib Tools*, pp. 26-31).

It should be noted that when zooming in on a section of any of the graphs (original, filtered, or integrated), the others are automatically updated. In other words, simply zooming in on one section will automatically adjust the time vector in the other graphs. This allows for a better analysis of the mass movement. On the other hand, it is important to reiterate that the parameters used in these examples are arbitrary, so it is up to the operator to adjust the values to better define the results for each event.

7.1.1.- Example of calculating a record in SAC format

a) SAC record graph with low-pass filter (*Lowpass*). Original signal.




Fig. 31 Example of the SAC record graph, original signal.

b) Zoom of the SAC record graph with filter (*Lowpass*). Filtered signal.




Fig. 32 Example of the SAC record graph with low-pass filter (Lowpass), at 0.86Hz and filter order 4. Trace number = 0.

c) SAC record graph with Lowpass filter. Signal integral.




Fig. 33 Example of SAC record graph, integrated signal.

d) Resulting SAC records graphs (Original, filtered, and integrated).




Fig. 34 Example of SAC recording graphs (original signal, filtered signal, and integrated signal).

7.1.2.- Example of calculation of a VLP event, record in MSEED format.

In the previous images the movement of mass is not appreciated, this occurs with the VLP events, which are presented below.

a) MSEED record graph with Lowpass filter. Original signal.




Fig. 35 Example of a MSEED record graph, with a Lowpass filter, original signal.

b) MSEED record graph with Lowpass filter. Filtered signal.




Fig. 36 Example of MSEED record graph, with low-pass filter, filtered signal.

c) MSEED record graph with Lowpass filter. Signal integral.




Fig. 37 Example of SAC record graph, integrated signal.

d) Resulting SAC records graphs (Original, filtered and integrated).




Fig. 38 Example of SAC recording graphs (original signal, filtered signal and integrated signal).

- e) Zoom of the MSEED log graphs with lowpass filter. Signals (Original, filtered and integrated).





Fig. 39 Example of Zoom of the MSEED record graph, with Lowpass filter at 0.02 Hz frequency and 4th order filter. The Matplotlib Zoom tool is selected, drawing a box in any of the two segments of the graph, the second one with the time vector adapts to the zoom of the first one.

8.- Toolbar of Graphs (Matplotlib Library).

In the construction of graphs, the *Matplotlib* library's graph screen has a set of very useful tools that allow you to visualize, edit, and save graphs in various formats. At the top of the Matplotlib graph screen that appears when a graph is created, there is a toolbar similar to the following:



From left to right, the icons representing the actions to be performed are:


1. [Reset original view](#): Restores all graphs to the initial state.
2. [Back to previous view](#): Preview of the selected graph.
3. [Forward to next view](#): Forward view of the next image.
4. [Left button pans, Right button zooms, x/y fixes axis, CTRL fixes aspect](#): Moves the graph and axes left or right, zooms in or out, fixes the x/y axis, and fixes the aspect with CTRL.
5. [Zoom to rectangle](#): Through a rectangle, zooms in on the selected graph.
6. [Configure subplots](#): Configuration of subplots (Borders and spacings).
7. [Edit axis, curve and image parameters](#): Editing the parameters of the graph. Select the axes or graph and edit elements such as title, coordinates (X, Y), and curve parameters (lines, markers) in styles, colors, and size.
8. [Save the figure](#): Saves the graph in several formats.

This document does not delve into each of them; it only highlights the use of those that are generally more commonly used, such as (1, 2, 5, 7, and 8).

In the above graphs, the use of the zoom tool (5) has been observed. Tools 2 and 3 allow zooming in or out individually for each graph. Option 1 allows restoring all elements or subplots of the graph to their initial values (*each individual graph or part of the window*). As for option 8, it allows saving the graph in various formats. The rest are straightforward, and it is up to the user to explore each of them. Now, the processes for "*editing*" and "*saving or storing*" the graphs (*Numbers 7 and 8*) are detailed below.

8.1.- Saving Graphs.

The process of saving graphs is very simple. Click on the icon of tool number 8 (Save the figure).



This opens an explorer window, similar to those in Windows (depending on the language or system used), where you can select the folder or directory where the graph will be saved.

Additionally, provide a name and select the desired format type. This can be done at the bottom of the explorer window (red circle in the image), where various format types available for saving are selected. The screen resembles the following.




Fig. 40 Screen that allows you to save the graph, selecting a name and choosing various format types. "Save" and "Cancel" buttons are provided to complete or cancel the process.




Fig. 41 Screen where you can see the types of formats available to save the graph.

The previous figure shows a list of the available file formats, the following image presents this list in more detail:





Fig. 42 List of available formats for saving the graph generated by the analysis.

Once you have selected both the name and the desired file format, and the location of the folder or directory where the graph will be saved, click the "Save" button (*See Fig. 40*), and the graph will be stored and available for further use as needed.

8.2.- Editing Axes and Images in Graphs.

Through the "Edit" button, point 7 (*See page 26*) of the graph toolbar (*Edit axis, curve and image parameters*), it is possible to edit or modify the parameters of the axes, images, and curves of the graphs.



For example, to modify the parameters of the image of a spectrogram, click on this command button. A "Customize" dialog box appears, indicating which of the "axes" in the graph areas you want to edit or modify. After selecting, click the "OK" button. This dialog box is similar to the following.




Fig. 43 Customize dialog box, the spectrogram axis has been selected.

Once the desired axis is selected, and the "OK" button is clicked, a new window with the options in the figure is presented. Here, various values of the selected axis are edited, in this case, the spectrogram (*Axes and Images*). The dialog box is as follows.




Fig. 44 Dialog box for editing options for the title and axes of the figure.

In this "*Axes*" section, as you can see, you can edit or modify the values or parameters of the title and the "*X*" and "*Y*" axes of the graph. For our example, we want to modify the image, so we will select the tab indicating this option. The image presented is as follows.




Fig. 45 Dialog box for editing options for image parameters.

As seen in the image, various parameters can be modified, including labels, the color map or "*Colormap*", used in the spectrogram, minimum and maximum values, and interpolation. The default value for the "*Colormap*" is set to "**jet**". The minimum and maximum values for this color map and the interpolation used are assigned by default to the image, but they can be modified according to the operator's interest.

The list of editable parameter values for both "*Colormap*" and "*Interpolation*" is presented in the figure on the next page.




Fig. 46 Dialog boxes for editing some of the parameters of "Colormap" and "Interpolation" to select in the graph.

CONCLUSION: The system is designed to be an easy-to-use, accessible and understandable tool. A user-friendly interface, which offers reliable technological assistance to the human operator in the analysis of seismic records, both tectonic and volcanic. This module allows the calculation and graphic representation of the integration of seismic signals. This helps in the understanding of signals such as VLP (*Very Long Period*) events. This allows the movement of masses within the volcanic edifice to be analyzed. The simplicity of this first version lies in the fact that it consists of a single module, which includes several filter analyses and the calculation of the integral applied to the analysis of a given seismic-volcanic signal. In later versions, extra modules may be added, containing various types of analysis for the progress of the study and research of the scientific community.

Acknowledgments:

This software and its documentation are the result of research from Spanish projects:

- a) PID2022-143083NB-I00, "LEARNING", funded by MCIN/AEI /10.13039/501100011033
- b) JMI and LG were partially funded by the Spanish project PROOF-FOREVER (EUR2022.134044)
- c) PRD was funded by the Ministerio de Ciencia e Innovación del Gobierno de España (MCIN), Agencia Estatal de Investigación (AEI), Fondo Social Europeo (FSE), and Programa Estatal de Promoción del Talento y su Empleabilidad en I+D+I Ayudas para contratos predoctorales para la formación de doctores 2020 (PRE2020-092719).
- d) Spanish Project PID2022-143083NB-I00 founded by MCIN/AEI/10.13039/501100011033 and by FEDER (EU) "Una manera de hacer Europa".

PLEC2022-009271 "DigiVolCa", funded by MCIN/AEI, funded by MCIN/AEI/10.13039/501100011033 and by EU «NextGenerationEU/PRTR», 10.13039/501100011033.

END of the document.



Ligdamis A. Gutiérrez E. PhD.

Theoretical and Cosmos Physics Department, Faculty of Sciences.

Geophysics Andalusian Institute.

Granada University (Ugr)

Granada, Spain – 2023



APPENDIX A

A1.- Installation of Python and Additional Libraries

A1.1. Package Content.

The main folder “*Analysis_System_1*”, It contains two folders with the programs (codes and interfaces in English and documentation in Spanish and English), organized as follows:

- a) Folder “*Reliable_set_tools_system_1*”: (*seismic analysis system assembly*). This folder must be copied to “*My Documents*”. Contains the following elements:
 - a. Subfolder: “*Images*” ” Images necessary for program interfaces.
 - b. Program: *Menu.py*. Startup program, presentation and calling of individual modules.
 - c. Program: “*Integrals_1.py*”. Main program for analysis and integration of seismic-volcanic events.
- b) Folders (*Document_ES* and *Document_EN*, depending on the language; *English* or *Spanish*). For *English* “*Document_EN*”: It consists of the following items:
 - a. User Manual for the module: “*5_Manual_Seismic Signals Integration System_EN.pdf*” in PDF, written in English, with the necessary documentation for the use of the system interfaces. In addition, the rest of the manuals for the other modules (1-10) that make up the system are found.
 - b. “*Initials Requirements.txt*” file. File containing the libraries needed to be installed on Windows through “Pip”, once Python is installed.
 - c. File “*README.txt*”: File with general instructions for system installation.
 - d. File “*Set_tools_System_1_1.bat*”, batch processing executable file. It must be copied to the desktop, from there by right clicking “run as administrator”, it will start the system by calling the main menu. The file will automatically search for the startup program (*Menu.py*) that is located in the “*Set_tools_System_1_1*” folder that has been previously copied to “*My Documents*” and will start Python, executing said program.

The system has all the elements (*programs and interfaces*) in English, except for the user manual, which is written in both Spanish and English. To install on Windows, two main actions should be taken after downloading and extracting the “. Rar” files. The first is to copy the entire folder (a) to the “*My Documents*” folder on the PC.

- a) From the main folder (*Analysis_System_1*), copy the subfolder “*Document_EN*” to “*My Documents*” in Windows.
- b) Copy the file “*Set_tools_System_1_1.bat*”, from the “(Document/Document_ES or Document_EN)”, depending on the version (Spanish or English), to the Windows desktop.

This ensures the proper use of the program. Now, we will proceed with the installation of the Python language and additional Python libraries on Windows.

A1.2.- Installing Python on Windows.

Python is an interpreted, multi-platform, and multiparadigm programming language (*it works on various operating systems, including Windows, Linux, and Mac*), utilizing two or more programming paradigms within a program-object-oriented, reflective, imperative, and functional.

In addition, Python can be enriched by a large number of programming modules, libraries, packages, or libraries installed through its package manager, "**Pip**." On Linux, the Python program and its manager "**Pip**" are installed together with the operating system. In Windows systems, however, where Python is not a native language, it is necessary to install this language beforehand by downloading the appropriate version from the Python distribution website at the following address: <https://www.python.org/downloads/>

On the website, the correct version should be selected based on the type of operating system on the computer, including whether it is 32 or 64 bits.

To be installed on both 32 and 64-bit systems, it is essential to note that this document and the software were created with the version available at that time, which was "[Python 3.8.6](#)", and many more versions have emerged since then. A more modern and adaptable version to the software (recommended) is "[Python 10.10](#)".

Users need to check if more advanced versions do not interfere with some of the installed libraries, such as "[Obspy](#)," for example. This is because everything related to Linux systems is constantly changing with updates that Python and Linux-based systems make. It is advisable to visit the website and download the most stable or tested updated version of Python that works well with this software.

Once downloaded, run it as an administrator (*right-click and "run as administrator"*), and the software installation wizard will guide you through the necessary steps (*just follow the instructions*).

The process takes only a few minutes. It is "recommended" to indicate during the process, when asked, to include an access path in the system's "**Path**" so that Python can be accessed from any location in Windows. If this is not done during the installation process, it must be done manually by modifying the environment variables (*more complicated*) to include the path from where Python is installed. This will not be necessary (*if indicated at the beginning*) through the installation wizard.

A1.3.- Installation of Additional Libraries.

The next step is to ensure that Python and its file manager or package manager (**Pip**) have been installed correctly. "**Pip**" (*file and library manager*) is crucial because it allows the installation of additional libraries that Python needs to run the created programs. To do this, open the Windows console window, or "**CMD**." The **CMD**, or command prompt, is a command-line interpreter.

Accessing the CMD is possible by typing, searching for the Windows logo key (a window), located between the "**Ctrl**" and "**Alt**" keys at the bottom left of the keyboard. Pressing this key, plus (+) the letter "**R**" key, will open a "**Run**" program window, similar to the following.






Fig. A1 Screen run in Windows. In the **red circle**, type "**cmd**" and click "**OK**."

As seen in the figure above, type "**cmd**," click "**OK**," which will open the Windows command prompt window.

Another way to do this is at the bottom of the desktop, in (W7) or next to (W10) the Windows "**Start**" button. There is the search section, indicated by the magnifying glass icon. This indicates a search for programs, similar to the following.



Fig. A2 Windows Program Search Screen.

In the box that says "Search programs and files" (Windows 7) or "*Type here to search*" (Windows 10), type "**cmd**" as well. This action or the previous one will bring up the Windows command prompt (**CMD**), similar to the following (W7).




Fig. A3 Windows 7 Command Prompt (CMD) Screen.

The same applies to versions: Windows 10 (W10) or Windows 11 (W11).



Fig. A4 Command Prompt (CMD) Screen in Windows 10.

Once on this screen, to verify that both Python and its package manager "[pip](#)" have been installed correctly, type the following commands: [Python -V](#), and to check "[pip](#)," type: [pip -V](#). This is shown in the following figure.



Fig. A5 CMD Screen, indicating Python and pip versions in Windows.

The output of typing "[-V](#)" in Python indicates invoking the installed version. In this case, it can be seen that it is "3.8.6" (*The library set is compatible with 3.10.10 version*). This has been possible from any location in the system because the Python script has been installed, remember, in the "**path**" or route found in the system's environment variables. Also, after typing "[pip -V](#)", it can be seen that the Pip version is "20.2.1." At this point, it is recommended to update this version since, by default, "[Pip](#)" is installed along with "[Python](#)", but it does not install the latest or most up-to-date version. To do this, in the CMD window or console, type the following command (Windows/Linux): On Windows, type "[python](#)," and on Linux, type "[python3](#)".

Windows: > [python -m pip install --upgrade pip](#) | **Linux:** \$ [sudo python3 -m pip install --upgrade pip](#)

This indicates that "[Pip](#)" will be updated to its most recent version (*On Linux, as a "superuser," i.e., with "sudo" at the beginning*). It is shown in the following screen.

```

C:\Users\Usuario>python -V
python 3.8.6

C:\Users\Usuario>pip -V
pip 20.2.1 from c:\users\usuario\appdata\local\programs\python\python38\lib\site-packages\pip (python 3.8)

C:\Users\Usuario>python -m pip install --upgrade pip
Collecting pip
  Downloading pip-21.0.1-py3-none-any.whl (1.5 MB)
    | 1.5 MB 2.2 MB/s
Installing collected packages: pip
  Attempting uninstall: pip
    Found existing installation: pip 20.2.1
    Uninstalling pip-20.2.1:
      Successfully uninstalled pip-20.2.1
  Successfully installed pip-21.0.1

C:\Users\Usuario>pip -V
pip 21.0.1 from c:\users\usuario\appdata\local\programs\python\python38\lib\site-packages\pip (python 3.8)

C:\Users\Usuario>

```

Fig. A6 Screen showing the update and verification of the new version of pip in Windows.

As can be seen, when typing again (**pip -V**), once Pip is updated, the version is 21.0.1. With this, Python and Pip are already installed and updated. Pip, as mentioned, is very important because with this manager, all the necessary libraries and packages are installed so that Python applications can be executed correctly and without errors. To use the system, you must proceed to install the necessary packages or libraries through Pip.

Next, we will proceed to explain how, in a simple and completely automatic way, the most commonly used and general libraries that Python needs will be installed on the system. Libraries such as, for example, "*obspy*," which is the open-source library or software based on Python for processing seismological data. Also, "*matplotlib*," which is a library for generating graphics from data contained in lists or arrays in Python and its mathematical extension "*NumPy*," among others, which the system needs for its execution (*See Annex B*).

A1.4 Automatic Installation of Libraries on Windows and Linux from PIP.

The advantage of having already installed and updated Pip in Windows is that you can install all the libraries that Python needs to run the system.

Additionally, in the "*Document*" folder, the "*Readme.txt*" file contains instructions for this installation. So the user only needs to follow the instructions, and the necessary packages will be installed on the computer (PC) automatically by Pip, both on Windows and Linux. The required libraries are in the file called "*Initial_requirements.txt*", included in the "*Document*" folder of the downloaded installation files and in **Annex B**.

In a Windows Command Prompt (**Cmd**) window, actions are taken for each of the commands indicated in the file, following the instructions. The installation should not present problems on Windows and Linux systems. If any library encounters an error during installation (*shown in red in CMD*), you should consult the documentation for that library or check if the correct or recommended version of Python is being installed (*version 3.8.6 and/or 3.10.10*). The installation on Linux systems (*See README.txt*) is similar and simpler. Copy the main folder to the desktop, the personal folder, etc. From that location, open a command prompt, and simply type:

"\$ python3 Menu.py" to start the system.

APPENDIX B:

INSTALL PYTHON LIBRARIES FOR THE PROPER FUNCTIONING OF THE SYSTEM.

1.- **PIP:** The **Pip** (*Preferred Installer Program*) is the package or package management manager used to install and manage software packages written in Python. When installing Python, Pip is installed by default. To check the version of Python or PIP, type the following in a console or CMD:

```
python -V / pip – And to see the list of installed pip packages: -> pip list
```

Usually, you need to update the version of pip with which Python is installed. For this, type the following command in the command prompt (CMD). In Linux and Mac systems, "**sudo**" is placed at the beginning to indicate super-user permissions.

```
Python –m pip install --upgrade pip / (LINUX) -> sudo python –m pip install --upgrade pip
```

Once downloaded and installed, you can check the version again with the first command, and you will see that the version has changed and been updated. Now that pip is updated, we will proceed to install the necessary packages for Python to work correctly with the applications.

2.- **PyQt Installation:** This is a Python binding for the Qt library written in the C++ language. It is used for creating and using graphical user interfaces (GUI) in Python. Type the following in the command prompt (CMD).

```
pip install PyQt5 / (LINUX & Mac) -> sudo python install PyQt5
```

3.- **Matplotlib library Installation.** Matplotlib is the library that allows the creation and visualization of graphics. Type the following:

```
pip install matplotlib / (LINUX & Mac) -> sudo python install matplotlib
```

4.- Install the **Obspy** library. This library is for handling seismic signals. Type the following:

```
pip install obspy / (LINUX & Mac) -> sudo python install obspy
```

5.- Install **Thinter**: Thinter is a graphical user interface (GUI). Type the following:

```
pip install tk / (LINUX & Mac) -> sudo python install tk
```

6.- Install **quantecon**: This library is used for spectrum estimation, Periodogram, Fourier transform. Type the following:

```
pip install --upgrade quantecon / (LINUX & Mac) -> sudo python install --upgrade quantecon
```

7.- Update a library for **matplotlib**. To avoid problems with graphics, install the following:

```
pip install msvc-runtime / (LINUX & Mac) -> sudo python install msvc-runtime
```

8.- Install **easygui** for the graphical interface:

```
pip install easygui / (LINUX & Mac) -> sudo python install easygui
```

9 Install **PyWavelets** for CWT handling.

```
pip install PyWavelets / (LINUX & Mac) -> sudo python install PyWavelets
```

10.- Install **plotly** for handling and assisting with graphics along with Matplotlib.

```
pip install plotly / (LINUX & Mac) -> sudo python install plotly
```

11.- Install "**pyaudio**", for audio management. Python bindings for PortAudio v19, the cross-platform audio I/O library

```
python -m pip install pyaudio / (LINUX & Mac) -> sudo apt-get install python3-pyaudio
```

Finally, type "**pip list**" to see the installed libraries. Optionally, you can create a file called "**requirements.txt**" that will contain all the libraries that the PC will use. The "**requirements.txt**" file must be in the current directory. The instruction to do this is as follows:

```
pip freeze > requirements.txt
```